SPARK MAX - Java Documentation

Generated by Doxygen 1.8.15

1 Hierarchical Index
1.1 Class Hierarchy
2 Class Index
2.1 Class List
3 Class Documentation
3.1 com.revrobotics.CANPIDController.AccelStrategy Enum Reference
3.2 com.revrobotics.CANDigitalInput Class Reference
3.2.1 Constructor & Destructor Documentation
3.2.1.1 CANDigitalInput()
3.2.2 Member Function Documentation
3.2.2.1 enableLimitSwitch()
3.2.2.2 get()
3.2.2.3 isLimitSwitchEnabled()
3.3 com.revrobotics.CANEncoder Class Reference
3.3.1 Constructor & Destructor Documentation
3.3.1.1 CANEncoder()
3.3.2 Member Function Documentation
3.3.2.1 getPosition()
3.3.2.2 getPositionConversionFactor()
3.3.2.3 getVelocity()
3.3.2.4 getVelocityConversionFactor()
3.3.2.5 setPosition()
3.3.2.6 setPositionConversionFactor()
3.3.2.7 setVelocityConversionFactor()
3.4 com.revrobotics.CANError Enum Reference
3.5 com.revrobotics.jni.CANHeartbeatJNI Class Reference
3.6 com.revrobotics.CANPIDController Class Reference
3.6.1 Constructor & Destructor Documentation
3.6.1.1 CANPIDController()
3.6.2 Member Function Documentation
3.6.2.1 getD() [1/2]
3.6.2.2 getD() [2/2]
3.6.2.3 getDFilter()
3.6.2.4 getFF() [1/2]
3.6.2.5 getFF() [2/2]
3.6.2.6 getl() [1/2] 14
3.6.2.7 getl() [2/2] 14
3.6.2.8 getlAccum()
3.6.2.9 getlMaxAccum()
3.6.2.10 getlZone() [1/2]1
3.6.2.11 getlZone() [2/2]

3.6.2.12 getOutputN	Max() [1/2]	16
3.6.2.13 getOutputN	Max() [2/2]	16
3.6.2.14 getOutputN	Min() [1/2]	17
3.6.2.15 getOutputN	Min() [2/2]	17
3.6.2.16 getP() [1/2	2]	18
3.6.2.17 getP() [2/2	2]	18
3.6.2.18 getSmartM	lotionAccelStrategy()	19
3.6.2.19 getSmartM	IotionAllowedClosedLoopError()	19
3.6.2.20 getSmartM	lotionMaxAccel()	19
3.6.2.21 getSmartM	lotionMaxVelocity()	20
3.6.2.22 getSmartM	IotionMinOutputVelocity()	20
3.6.2.23 setD() [1/2	2]	20
3.6.2.24 setD() [2/2	2]	21
3.6.2.25 setDFilter()	[1/2]	21
3.6.2.26 setDFilter()	[2/2]	22
3.6.2.27 setFF() [1,	/2]	22
3.6.2.28 setFF() [2,	/2]	22
3.6.2.29 setl() [1/2	1	23
3.6.2.30 setl() [2/2	1	23
3.6.2.31 setIAccum	0	24
3.6.2.32 setIMaxAcc	cum()	24
3.6.2.33 setIZone()	[1/2]	24
3.6.2.34 setIZone()	[2/2]	25
3.6.2.35 setOutputF	Range() [1/2]	25
3.6.2.36 setOutputF	Range() [2/2]	26
3.6.2.37 setP() [1/2	2]	26
3.6.2.38 setP() [2/2	2]	27
3.6.2.39 setReferen	nce() [1/3]	27
3.6.2.40 setReferen	rce() [2/3]	28
3.6.2.41 setReferen	rce() [3/3]	28
3.6.2.42 setSmartM	lotionAccelStrategy()	29
3.6.2.43 setSmartM	lotionAllowedClosedLoopError()	29
3.6.2.44 setSmartM	lotionMaxAccel()	30
3.6.2.45 setSmartM	lotionMaxVelocity()	30
3.6.2.46 setSmartM	lotionMinOutputVelocity()	30
3.7 com.revrobotics.CANSparkMa	ax Class Reference	31
3.7.1 Constructor & Destruc	ctor Documentation	32
3.7.1.1 CANSparkN	flax()	32
3.7.2 Member Function Doc	cumentation	32
3.7.2.1 burnFlash()		33
3.7.2.2 clearFaults())	33
3.7.2.3 close()		33

33
33
33
34
34
35
35
35
36
36
36
36
36
37
37
37
38
38
38
38
39
39
40
40
40
41
41
41
41
42
42
42
43
43
44
45
45
46
47
48
48
49

	3.9.2.1 getDeviceId()	49
	3.9.2.2 getFirmwareString()	49
	3.9.2.3 getFirmwareVersion()	49
	3.9.2.4 getMotorType()	49
	3.9.2.5 getSerialNumber()	50
	3.9.2.6 restoreFactoryDefaults() [1/2]	50
	3.9.2.7 restoreFactoryDefaults() [2/2]	50
	3.9.2.8 setMotorType()	50
	3.9.2.9 setPeriodicFramePeriod()	51
	3.10 com.revrobotics.CANSparkMaxLowLevel.ConfigParameter Enum Reference	51
	3.11 com.revrobotics.ControlType Enum Reference	54
	3.12 com.revrobotics.CANSparkMaxFrames.DataFrame Interface Reference	54
	3.13 com.revrobotics.CANSparkMax.FaultID Enum Reference	55
	3.14 com.revrobotics.CANSparkMax.IdleMode Enum Reference	55
	3.15 com.revrobotics.CANSparkMax.InputMode Enum Reference	56
	3.16 com.revrobotics.CANDigitalInput.LimitSwitch Enum Reference	56
	3.17 com.revrobotics.CANDigitalInput.LimitSwitchPolarity Enum Reference	57
	3.18 com.revrobotics.CANSparkMaxLowLevel.MotorType Enum Reference	57
	3.19 com.revrobotics.CANSparkMaxLowLevel.ParameterStatus Enum Reference	57
	3.20 com.revrobotics.CANSparkMaxLowLevel.ParameterType Enum Reference	58
	3.21 com.revrobotics.CANSparkMaxLowLevel.PeriodicFrame Enum Reference	58
	3.22 com.revrobotics.CANSparkMaxLowLevel.PeriodicStatus0 Class Reference	59
	3.23 com.revrobotics.CANSparkMaxLowLevel.PeriodicStatus1 Class Reference	59
	3.24 com.revrobotics.CANSparkMaxLowLevel.PeriodicStatus2 Class Reference	59
	3.25 com.revrobotics.jni.RevJNIWrapper Class Reference	59
	3.26 com.revrobotics.CANSparkMax.SensorType Enum Reference	60
1		~-
ın	dex	61

Chapter 1

Hierarchical Index

1.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

2 Hierarchical Index

Chapter 2

Class Index

2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

com.revrobotics.CANPIDController.AccelStrategy
com.revrobotics.CANDigitalInput
com.revrobotics.CANEncoder
com.revrobotics.CANError
com.revrobotics.jni.CANHeartbeatJNI
com.revrobotics.CANPIDController
com.revrobotics.CANSparkMax
com.revrobotics.CANSparkMaxFrames
com.revrobotics.CANSparkMaxLowLevel
com.revrobotics.CANSparkMaxLowLevel.ConfigParameter
com.revrobotics.ControlType
com.revrobotics.CANSparkMaxFrames.DataFrame
com.revrobotics.CANSparkMax.FaultID
com.revrobotics.CANSparkMax.IdleMode
com.revrobotics.CANSparkMax.InputMode
com.revrobotics.CANDigitalInput.LimitSwitch 56
com.revrobotics.CANDigitalInput.LimitSwitchPolarity
com.revrobotics.CANSparkMaxLowLevel.MotorType
com.revrobotics.CANSparkMaxLowLevel.ParameterStatus
com.revrobotics.CANSparkMaxLowLevel.ParameterType
com.revrobotics.CANSparkMaxLowLevel.PeriodicFrame58
com.revrobotics.CANSparkMaxLowLevel.PeriodicStatus0
com.revrobotics.CANSparkMaxLowLevel.PeriodicStatus1
com.revrobotics.CANSparkMaxLowLevel.PeriodicStatus2
com.revrobotics.jni.RevJNIWrapper
com revrobotics CANSparkMax SensorType 60

4 Class Index

Chapter 3

Class Documentation

3.1 com.revrobotics.CANPIDController.AccelStrategy Enum Reference

Public Member Functions

· AccelStrategy (int value)

Static Public Member Functions

• static AccelStrategy fromInt (int value)

Public Attributes

- kTrapezoidal =(0)
- **kSCurve** =(1)
- final int value

The documentation for this enum was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANPIDController.java

3.2 com.revrobotics.CANDigitalInput Class Reference

Classes

- enum LimitSwitch
- enum LimitSwitchPolarity

Public Member Functions

- CANDigitaIInput (CANSparkMax device, LimitSwitch limitSwitch, LimitSwitchPolarity polarity)
- boolean get ()
- CANError enableLimitSwitch (boolean enable)
- boolean isLimitSwitchEnabled ()

3.2.1 Constructor & Destructor Documentation

3.2.1.1 CANDigitalInput()

Constructs a CANDigitalInput.

Parameters

device	The Spark Max to which the limit switch is attached.
limitSwitch	Whether this is forward or reverse limit switch.
polarity	Whether the limit switch is normally open or normally closed.

3.2.2 Member Function Documentation

3.2.2.1 enableLimitSwitch()

Enables or disables controller shutdown based on limit switch.

Parameters

enable	Enable/disable motor shutdown based on limit switch state. This does not effect the result of the get()
	command.

Returns

CANError Set to CANError::kOk if successful

3.2.2.2 get()

```
boolean com.revrobotics.CANDigitalInput.get ( )
```

Get the value from a digital input channel.

Retrieve the value of a single digital input channel from a motor controller. This method will return the state of the limit input based on the selected polarity, whether or not it is enabled.

Returns

The state of the limit switch based on the configured polarity

3.2.2.3 isLimitSwitchEnabled()

```
boolean com.revrobotics.CANDigitalInput.isLimitSwitchEnabled ( )
```

Returns

True if limit switch is enabled

The documentation for this class was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANDigitalInput.java

3.3 com.revrobotics.CANEncoder Class Reference

Public Member Functions

- CANEncoder (CANSparkMax device)
- double getPosition ()
- double getVelocity ()
- CANError setPosition (double position)
- CANError setPositionConversionFactor (double factor)
- CANError setVelocityConversionFactor (double factor)
- double getPositionConversionFactor ()
- double getVelocityConversionFactor ()

3.3.1 Constructor & Destructor Documentation

3.3.1.1 CANEncoder()

Constructs a CANPIDController.

Parameters

device The Spark Max to which the encoder is attached.

3.3.2 Member Function Documentation

3.3.2.1 getPosition()

```
double com.revrobotics.CANEncoder.getPosition ( )
```

Get the position of the motor. This returns the native units of 'rotations' by default, and can be changed by a scale factor using setPositionConversionFactor().

Returns

Number of rotations of the motor

3.3.2.2 getPositionConversionFactor()

```
double com.revrobotics.CANEncoder.getPositionConversionFactor ( )
```

Get the conversion factor for position of the encoder. Multiplied by the native output units to give you position

Returns

The conversion factor for position

3.3.2.3 getVelocity()

```
double com.revrobotics.CANEncoder.getVelocity ( )
```

Get the velocity of the motor. This returns the native units of 'RPM' by default, and can be changed by a scale factor using setVelocityConversionFactor().

Returns

Number the RPM of the motor

3.3.2.4 getVelocityConversionFactor()

```
double com.revrobotics.CANEncoder.getVelocityConversionFactor ( )
```

Get the conversion factor for velocity of the encoder. Multiplied by the native output units to give you velocity

Returns

The conversion factor for velocity

3.3.2.5 setPosition()

```
CANError com.revrobotics.CANEncoder.setPosition (
double position)
```

Set the position of the encoder. By default the units are 'rotations' and can be changed by a scale factor using setPositionConversionFactor().

Parameters

position	Number of rotations of the motor	
----------	----------------------------------	--

Returns

CANError Set to CANError.kOk if successful

3.3.2.6 setPositionConversionFactor()

```
CANError com.revrobotics.CANEncoder.setPositionConversionFactor ( {\tt double} \  \, \textit{factor} \  \, )
```

Set the conversion factor for position of the encoder. Multiplied by the native output units to give you position.

Parameters

	factor	The conversion factor to multiply the native units by
--	--------	---

Returns

CANError Set to CANError.kOk if successful

3.3.2.7 setVelocityConversionFactor()

```
CANError com.revrobotics.CANEncoder.setVelocityConversionFactor ( double factor )
```

Set the conversion factor for velocity of the encoder. Multiplied by the native output units to give you velocity

Parameters

factor	The conversion factor to multiply the native units by
--------	---

Returns

CANError Set to CANError.kOk if successful

The documentation for this class was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANEncoder.java

3.4 com.revrobotics.CANError Enum Reference

D.	- I I	15 -		ш.	ما ن		tes
	ını			TTI	rı n	и.	TOC.
Гι	a wi		$\overline{}$	LLI	III	u	LCO

- kOK
- kError
- kTimeout

The documentation for this enum was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANError.java

3.5 com.revrobotics.jni.CANHeartbeatJNI Class Reference

Inherits com.revrobotics.jni.RevJNIWrapper.

Static Public Member Functions

- static native void HeartbeatInit ()
- static native int RunHeartbeat ()
- static native void RegisterDevice (int deviceID)
- static native void **UnregisterDevice** (int deviceID)

The documentation for this class was generated from the following file:

C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/jni/CANHeartbeatJNI.java

3.6 com.revrobotics.CANPIDController Class Reference

Classes

enum AccelStrategy

Public Member Functions

- CANPIDController (CANSparkMax device)
- CANError setReference (double value, ControlType ctrl)
- CANError setReference (double value, ControlType ctrl, int pidSlot)
- CANError setReference (double value, ControlType ctrl, int pidSlot, double arbFeedforward)
- CANError setP (double gain)
- CANError setP (double gain, int slotID)
- · CANError set! (double gain)
- CANError setI (double gain, int slotID)
- CANError setD (double gain)
- CANError setD (double gain, int slotID)
- CANError setDFilter (double gain)
- CANError setDFilter (double gain, int slotID)
- CANError setFF (double gain)
- CANError setFF (double gain, int slotID)
- CANError setIZone (double IZone)
- CANError setIZone (double IZone, int slotID)
- CANError setOutputRange (double min, double max)
- CANError setOutputRange (double min, double max, int slotID)
- double getP ()
- double getP (int slotID)
- double getI ()
- double getI (int slotID)
- double getD ()
- double getD (int slotID)
- double getDFilter (int slotID)
- double getFF ()
- double getFF (int slotID)
- double getIZone ()
- double getIZone (int slotID)
- double getOutputMin ()
- double getOutputMin (int slotID)
- double getOutputMax ()
- double getOutputMax (int slotID)
- CANError setSmartMotionMaxVelocity (double maxVel, int slotID)
- CANError setSmartMotionMaxAccel (double maxAccel, int slotID)
- $\bullet \ \ CANError\ setSmartMotionMinOutputVelocity\ (double\ minVel,\ int\ slotID)$
- $\bullet \ \ CANError\ set Smart Motion Allowed Closed Loop Error\ (double\ allowed Err,\ int\ slot ID)$
- CANError setSmartMotionAccelStrategy (AccelStrategy accelStrategy, int slotID)
- double getSmartMotionMaxVelocity (int slotID)
- double getSmartMotionMaxAccel (int slotID)
- double getSmartMotionMinOutputVelocity (int slotID)
- double getSmartMotionAllowedClosedLoopError (int slotID)
- AccelStrategy getSmartMotionAccelStrategy (int slotID)
- CANError setIMaxAccum (double iMaxAccum, int slotID)
- double getIMaxAccum (int slotID)
- CANError setIAccum (double iAccum)
- double getIAccum ()

3.6.1 Constructor & Destructor Documentation

3.6.1.1 CANPIDController()

```
{\tt com.revrobotics.CANPIDController.CANPIDController} \  \, ( \\ {\tt CANSparkMax} \  \, device \ )
```

Constructs a CANPIDController.

Parameters

```
device The Spark Max this object configures.
```

3.6.2 Member Function Documentation

```
3.6.2.1 getD() [1/2]
double com.revrobotics.CANPIDController.getD ( )
```

Get the Derivative Gain constant of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Returns

double D Gain value

Get the Derivative Gain constant of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Parameters

slo	oti	D
-----	-----	---

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

double D Gain value

3.6.2.3 getDFilter()

Get the Derivative Filter constant of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

double D Filter value

```
3.6.2.4 getFF() [1/2]
double com.revrobotics.CANPIDController.getFF ( )
```

Get the Feed-forward Gain constant of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Returns

double F Gain value

Get the Feed-forward Gain constant of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

double F Gain value

```
3.6.2.6 getl() [1/2]
double com.revrobotics.CANPIDController.getI ( )
```

Get the Integral Gain constant of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Returns

double I Gain value

Get the Integral Gain constant of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

double I Gain value

3.6.2.8 getIAccum()

```
double com.revrobotics.CANPIDController.getIAccum ( )
```

Get the I accumulator of the PID controller. This is useful when wishing to see what the I accumulator value is to help with PID tuning

Returns

The value of the I accumulator

3.6.2.9 getIMaxAccum()

```
double com.revrobotics.CANPIDController.getIMaxAccum ( int \ slotID \ )
```

Get the maximum I accumulator of the PID controller. This value is used to constrain the I accumulator to help manage integral wind-up

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

The max value to contrain the I accumulator to

```
3.6.2.10 getlZone() [1/2]
```

```
double com.revrobotics.CANPIDController.getIZone ( )
```

Get the IZone constant of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Returns

double IZone value

Get the IZone constant of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

double IZone value

```
3.6.2.12 getOutputMax() [1/2]
double com.revrobotics.CANPIDController.getOutputMax ( )
```

Get the max output of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Returns

double max value

Get the max output of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

double max value

```
3.6.2.14 getOutputMin() [1/2]
double com.revrobotics.CANPIDController.getOutputMin ( )
```

Get the derivative filter constant of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

double D FilterGet the min output of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Returns

double min value

Get the min output of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

double min value

```
3.6.2.16 getP() [1/2]
double com.revrobotics.CANPIDController.getP ( )
```

Get the Proportional Gain constant of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Returns

double P Gain value

Get the Proportional Gain constant of the PIDF controller on the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

double P Gain value

3.6.2.18 getSmartMotionAccelStrategy()

```
AccelStrategy com.revrobotics.CANPIDController.getSmartMotionAccelStrategy ( int \ slotID \ )
```

Get the acceleration strategy used to control acceleration on the motor. The current strategy is trapezoidal motion profiling.

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

The acceleration strategy to use for the automatically generated motion profile.

3.6.2.19 getSmartMotionAllowedClosedLoopError()

```
\label{lowedClosedLoopError} \mbox{double com.revrobotics.CANPIDController.getSmartMotionAllowedClosedLoopError (} \\ \mbox{int } slotID \mbox{)}
```

Get the allowed closed loop error of SmartMotion mode. This value is how much deviation from your setpoint is tolerated and is useful in preventing oscillation around your setpoint.

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

The allowed deviation for your setpoint vs actual position in rotations

3.6.2.20 getSmartMotionMaxAccel()

```
double com.revrobotics.CANPIDController.getSmartMotionMaxAccel ( int\ slot TD\ )
```

Get the maximum acceleration of the SmartMotion mode. This is the accleration that the motor velocity will increase at until the max velocity is reached

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

The maxmimum acceleration for the motion profile in RPM per second

3.6.2.21 getSmartMotionMaxVelocity()

```
double com.revrobotics.CANPIDController.getSmartMotionMaxVelocity ( int \ \textit{slotID} \ )
```

Get the maximum velocity of the SmartMotion mode. This is the velocity that is reached in the middle of the profile and is what the motor should spend most of its time at

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

The maxmimum cruise velocity for the motion profile in RPM

3.6.2.22 getSmartMotionMinOutputVelocity()

```
double com.revrobotics.CANPIDController.getSmartMotionMinOutputVelocity ( int \ \textit{slotID} \ )
```

Get the mimimum velocity of the SmartMotion mode. Any requested velocities below this value will be set to 0.

Parameters

slotID

Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

The minimum velocity for the motion profile in RPM

Set the Derivative Gain constant of the PIDF controller on the SPARK MAX. This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burnFlash() is called. The recommended method to configure this parameter is use to SPARK MAX GUI to tune and save parameters.

Parameters

Returns

CANError Set to REV_OK if successful

Set the Derivative Gain constant of the PIDF controller on the SPARK MAX. This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burnFlash() is called. The recommended method to configure this parameter is use to SPARK MAX GUI to tune and save parameters.

Parameters

gain	The derivative gain value, must be positive	
slotID	Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().	

Returns

CANError Set to REV_OK if successful

Set the Derivative Filter constant of the PIDF controller on the SPARK MAX. This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burnFlash() is called.

Parameters

gain	The derivative filter value, must be a positive number between 0 and 1
------	--

Returns

CANError Set to REV_OK if successful

Set the Derivative Filter constant of the PIDF controller on the SPARK MAX. This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burnFlash() is called.

Parameters

gain	The derivative filter value, must be a positive number between 0 and 1	
slotID	D Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain	
	values and can be changed in each control frame using SetReference().	

Returns

CANError Set to REV_OK if successful

Set the Feed-froward Gain constant of the PIDF controller on the SPARK MAX. This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burnFlash() is called. The recommended method to configure this parameter is use to SPARK MAX GUI to tune and save parameters.

Parameters

gain The feed-forward gain value	
----------------------------------	--

Returns

CANError Set to REV_OK if successful

Set the Feed-froward Gain constant of the PIDF controller on the SPARK MAX. This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burnFlash() is called. The recommended method to configure this parameter is use to SPARK MAX GUI to tune and save parameters.

Parameters

gain	The feed-forward gain value		
slotID	Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain		
	values and can be changed in each control frame using SetReference().		

Returns

CANError Set to REV OK if successful

Set the Integral Gain constant of the PIDF controller on the SPARK MAX. This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burnFlash() is called. The recommended method to configure this parameter is use to SPARK MAX GUI to tune and save parameters.

Parameters

gair	7	The integral gain value, must be positive
------	---	---

Returns

CANError Set to REV_OK if successful

Set the Integral Gain constant of the PIDF controller on the SPARK MAX. This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burnFlash() is called. The recommended method to configure this parameter is use to SPARK MAX GUI to tune and save parameters.

Parameters

gain	The integral gain value, must be positive	
slotID	Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain	
	values and can be changed in each control frame using SetReference().	

Returns

CANError Set to REV_OK if successful

3.6.2.31 setIAccum()

Set the I accumulator of the PID controller. This is useful when wishing to force a reset on the I accumulator of the PID controller. You can also preset values to see how it will respond to certain I characteristics

To use this function, the controller must be in a closed loop control mode by calling setReference()

Parameters

	iAccum	The value to set the I accumulator to
--	--------	---------------------------------------

Returns

CANError Set to kOK if successful

3.6.2.32 setIMaxAccum()

```
CANError com.revrobotics.CANPIDController.setIMaxAccum ( double iMaxAccum, int slotID )
```

Configure the maximum I accumulator of the PID controller. This value is used to constrain the I accumulator to help manage integral wind-up

Parameters

iMaxAccum	The max value to contrain the I accumulator to	
slotID	Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of	
	gain values and can be changed in each control frame using SetReference().	

Returns

CANError Set to kOK if successful

```
3.6.2.33 setIZone() [1/2]
```

```
CANError com.revrobotics.CANPIDController.setIZone ( double IZone )
```

Set the IZone range of the PIDF controller on the SPARK MAX. This value specifies the range the |error| must be within for the integral constant to take effect.

This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burn ← Flash() is called. The recommended method to configure this parameter is to use the SPARK MAX GUI to tune and save parameters.

Parameters

IZone	The IZone value, must be positive. Set to 0 to disable
-------	--

Returns

CANError Set to REV_OK if successful

Set the IZone range of the PIDF controller on the SPARK MAX. This value specifies the range the |error| must be within for the integral constant to take effect.

This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burn ← Flash() is called. The recommended method to configure this parameter is to use the SPARK MAX GUI to tune and save parameters.

Parameters

IZone	The IZone value, must be positive. Set to 0 to disable
slotID	Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain
	values and can be changed in each control frame using SetReference().

Returns

CANError Set to REV_OK if successful

Set the min amd max output for the closed loop mode.

This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burn ← Flash() is called. The recommended method to configure this parameter is to use the SPARK MAX GUI to tune and save parameters.

Parameters

min	Reverse power minimum to allow the controller to output
max	Forward power maximum to allow the controller to output

Returns

CANError Set to REV_OK if successful

```
3.6.2.36 setOutputRange() [2/2]
```

Set the min amd max output for the closed loop mode.

This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burn ← Flash() is called. The recommended method to configure this parameter is to use the SPARK MAX GUI to tune and save parameters.

Parameters

min	Reverse power minimum to allow the controller to output
max	Forward power maximum to allow the controller to output
slotID	Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

CANError Set to REV_OK if successful

Set the Proportional Gain constant of the PIDF controller on the SPARK MAX. This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burnFlash() is called. The recommended method to configure this parameter is use to SPARK MAX GUI to tune and save parameters.

Parameters

gain The proportional gain value, must be positive
--

Returns

CANError Set to REV_OK if successful

Set the Proportional Gain constant of the PIDF controller on the SPARK MAX. This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burnFlash() is called. The recommended method to configure this parameter is use to SPARK MAX GUI to tune and save parameters.

Parameters

gain	The proportional gain value, must be positive
slotID	Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain
	values and can be changed in each control frame using SetReference().

Returns

CANError Set to REV_OK if successful

Set the controller reference value based on the selected control mode.

Parameters

value	The value to set depending on the control mode. For basic duty cycle control this should be a value between -1 and 1 Otherwise: Voltage Control: Voltage (volts) Velocity Control: Velocity (RPM) Position Control: Position (Rotations) Current Control: Current (Amps). Native units can be changed using the setPositionConversionFactor() or setVelocityConversionFactor() methods of the CANEncoder class
ctrl	Is the control type

Returns

CANError Set to REV_OK if successful

Set the controller reference value based on the selected control mode. This will override the pre-programmed control mode but not change what is programmed to the controller.

Parameters

value	The value to set depending on the control mode. For basic duty cycle control this should be a value
	between -1 and 1 Otherwise: Voltage Control: Voltage (volts) Velocity Control: Velocity (RPM)
	Position Control: Position (Rotations) Current Control: Current (Amps). Native units can be changed
	using the setPositionConversionFactor() or setVelocityConversionFactor() methods of the
	CANEncoder class
ctrl	Is the control type to override with
pidSlot	for this command

Returns

CANError Set to REV_OK if successful

Set the controller reference value based on the selected control mode. This will override the pre-programmed control mode but not change what is programmed to the controller.

Parameters

value	The value to set depending on the control mode. For basic duty cycle control this should be a value between -1 and 1 Otherwise: Voltage Control: Voltage (volts) Velocity Control: Velocity (RPM) Position Control: Position (Rotations) Current Control: Current (Amps). Native units can be changed using the setPositionConversionFactor() or setVelocityConversionFactor() methods of the CANEncoder class
ctrl	Is the control type to override with
pidSlot	for this command
arbFeedforward	A value from which is represented in voltage applied to the motor after the result of the specified control mode. The units for the parameter is Volts. This value is set after the control mode, but before any current limits or ramp rates.

Returns

CANError Set to REV_OK if successful

3.6.2.42 setSmartMotionAccelStrategy()

```
CANError com.revrobotics.CANPIDController.setSmartMotionAccelStrategy ( {\tt AccelStrategy}~accelStrategy,\\ {\tt int}~slotID~)
```

Coming soon. Configure the acceleration strategy used to control acceleration on the motor. The current strategy is trapezoidal motion profiling.

Parameters

accelStrategy	The acceleration strategy to use for the automatically generated motion profile
slotID	Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of
	gain values and can be changed in each control frame using SetReference().

Returns

CANError Set to kOK if successful

3.6.2.43 setSmartMotionAllowedClosedLoopError()

Configure the allowed closed loop error of SmartMotion mode. This value is how much deviation from your setpoint is tolerated and is useful in preventing oscillation around your setpoint.

Parameters

allowedErr	The allowed deviation for your setpoint vs actual position in rotations
slotID	Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of
	gain values and can be changed in each control frame using SetReference().

Returns

CANError Set to kOK if successful

3.6.2.44 setSmartMotionMaxAccel()

Configure the maximum acceleration of the SmartMotion mode. This is the accleration that the motor velocity will increase at until the max velocity is reached

Parameters

maxAccel	The maxmimum acceleration for the motion profile in RPM per second
slotID	Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain
	values and can be changed in each control frame using SetReference().

Returns

CANError Set to kOK if successful

3.6.2.45 setSmartMotionMaxVelocity()

Configure the maximum velocity of the SmartMotion mode. This is the velocity that is reached in the middle of the profile and is what the motor should spend most of its time at

Parameters

maxVel	The maxmimum cruise velocity for the motion profile in RPM
slotID	Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain values and can be changed in each control frame using SetReference().

Returns

CANError Set to kOK if successful

3.6.2.46 setSmartMotionMinOutputVelocity()

```
CANError com.revrobotics.CANPIDController.setSmartMotionMinOutputVelocity ( double minVel, int slotID )
```

Configure the mimimum velocity of the SmartMotion mode. Any requested velocities below this value will be set to 0

Parameters

n	ninVel	The minimum velocity for the motion profile in RPM	
s	lotID	Is the gain schedule slot, the value is a number between 0 and 3. Each slot has its own set of gain	
		values and can be changed in each control frame using SetReference().	

Returns

CANError Set to kOK if successful

The documentation for this class was generated from the following file:

C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANPIDController.java

3.7 com.revrobotics.CANSparkMax Class Reference

Inherits com.revrobotics.CANSparkMaxLowLevel, and AutoCloseable.

Classes

- · class ExternalFollower
- enum FaultID
- enum IdleMode
- enum InputMode
- enum SensorType

Public Member Functions

- CANSparkMax (int deviceID, MotorType type)
- void close ()
- void set (double speed)
- double get ()
- void setInverted (boolean isInverted)
- boolean getInverted ()
- void disable ()
- void stopMotor ()
- · void pidWrite (double output)
- CANEncoder getEncoder ()
- CANPIDController getPIDController ()
- CANDigitalInput getForwardLimitSwitch (CANDigitalInput.LimitSwitchPolarity polarity)
- CANDigitalInput getReverseLimitSwitch (CANDigitalInput.LimitSwitchPolarity)
- · CANError setSmartCurrentLimit (int limit)
- CANError setSmartCurrentLimit (int stallLimit, int freeLimit)
- CANError setSmartCurrentLimit (int stallLimit, int freeLimit, int limitRPM)
- CANError setSecondaryCurrentLimit (double limit)
- CANError setSecondaryCurrentLimit (double limit, int chopCycles)
- CANError setIdleMode (IdleMode mode)
- IdleMode getIdleMode ()
- CANError enableVoltageCompensation (double nominalVoltage)

- CANError disableVoltageCompensation ()
- double getVoltageCompensationNominalVoltage ()
- CANError setOpenLoopRampRate (double rate)
- CANError setClosedLoopRampRate (double rate)
- double getOpenLoopRampRate ()
- double getClosedLoopRampRate ()
- CANError follow (final CANSparkMax leader)
- CANError follow (final CANSparkMax leader, boolean invert)
- CANError follow (ExternalFollower leader, int deviceID)
- CANError follow (ExternalFollower leader, int deviceID, boolean invert)
- boolean isFollower ()
- short getFaults ()
- short getStickyFaults ()
- boolean getFault (FaultID faultID)
- boolean getStickyFault (FaultID faultID)
- double getBusVoltage ()
- double getAppliedOutput ()
- double getOutputCurrent ()
- double getMotorTemperature ()
- CANError clearFaults ()
- CANError burnFlash ()
- CANError setCANTimeout (int milliseconds)

Additional Inherited Members

3.7.1 Constructor & Destructor Documentation

3.7.1.1 CANSparkMax()

Create a new SPARK MAX Controller

Parameters

deviceID	The device ID.	
type	The motor type connected to the controller. Brushless motors must be connected to their matching color and the hall sensor plugged in. Brushed motors must be connected to the Red and Black terminals only.	

3.7.2 Member Function Documentation

```
3.7.2.1 burnFlash()
CANError com.revrobotics.CANSparkMax.burnFlash ( )
Writes all settings to flash.
Returns
     CANError Set to CANError.kOk if successful
3.7.2.2 clearFaults()
CANError com.revrobotics.CANSparkMax.clearFaults ( )
Clears all sticky faults.
Returns
     CANError Set to CANError.kOk if successful
3.7.2.3 close()
void com.revrobotics.CANSparkMax.close ( )
Closes the SPARK MAX Controller
3.7.2.4 disable()
void com.revrobotics.CANSparkMax.disable ( )
Common interface for disabling a motor.
3.7.2.5 disableVoltageCompensation()
CANError com.revrobotics.CANSparkMax.disableVoltageCompensation ( )
Disables the voltage compensation setting for all modes on the SPARK MAX.
Returns
     CANError Set to CANError.kOk if successful
3.7.2.6 enableVoltageCompensation()
```

Sets the voltage compensation setting for all modes on the SPARK MAX and enables voltage compensation.

CANError com.revrobotics.CANSparkMax.enableVoltageCompensation (

double nominalVoltage)

Parameters

Returns

CANError Set to CANError.kOk if successful

Causes this controller's output to mirror the provided leader.

Only voltage output is mirrored. Settings changed on the leader do not affect the follower.

Parameters

N.
N

Returns

CANError Set to CANError.kOk if successful

Causes this controller's output to mirror the provided leader.

Only voltage output is mirrored. Settings changed on the leader do not affect the follower.

Parameters

leadei	The motor controller to follow.
invert	Set the follower to output opposite of the leader

Returns

CANError Set to CANError.kOk if successful

Causes this controller's output to mirror the provided leader.

Only voltage output is mirrored. Settings changed on the leader do not affect the follower.

Parameters

leader	The type of motor controller to follow (Talon SRX, Spark Max, etc.).
deviceID	The CAN ID of the device to follow.

Returns

CANError Set to CANError.kOk if successful

Causes this controller's output to mirror the provided leader.

Only voltage output is mirrored. Settings changed on the leader do not affect the follower.

Parameters

leader	The type of motor controller to follow (Talon SRX, Spark Max, etc.).
deviceID	The CAN ID of the device to follow.
invert	Set the follower to output opposite of the leader

Returns

CANError Set to CANError.kOk if successful

```
3.7.2.11 get()
```

```
double com.revrobotics.CANSparkMax.get ( )
```

Common interface for getting the current set speed of a speed controller.

Returns

The current set speed. Value is between -1.0 and 1.0.

3.7.2.12 getAppliedOutput()

```
double com.revrobotics.CANSparkMax.getAppliedOutput ( )
```

Returns

The motor controller's applied output duty cycle.

3.7.2.13 getBusVoltage()

```
double com.revrobotics.CANSparkMax.getBusVoltage ( )
```

Returns

The voltage fed into the motor controller.

3.7.2.14 getClosedLoopRampRate()

```
\verb|double com.revrobotics.CANSparkMax.getClosedLoopRampRate ( )|\\
```

Get the configured closed loop ramp rate

This is the maximum rate at which the motor controller's output is allowed to change.

Returns

ramp rate time in seconds to go from 0 to full throttle.

3.7.2.15 getEncoder()

```
CANEncoder com.revrobotics.CANSparkMax.getEncoder ( )
```

Returns

An object for interfacing with the integrated encoder.

3.7.2.16 getFault()

```
boolean com.revrobotics.CANSparkMax.getFault ( {\tt FaultID} \  \, \textit{faultID} \  \, )
```

Get the value of a specific fault

Parameters

faultID The ID of the fault to retrive	,
--	---

Returns

True if the fault with the given ID occurred.

3.7.2.17 getFaults()

```
short com.revrobotics.CANSparkMax.getFaults ( )
```

Returns

All fault bits as a short

3.7.2.18 getForwardLimitSwitch()

Returns

An object for interfacing with the integrated forward limit switch.

Parameters

polarity Whether the limit switch is normally open or normally cl

3.7.2.19 getIdleMode()

```
IdleMode com.revrobotics.CANSparkMax.getIdleMode ( )
```

Gets the idle mode setting for the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Returns

IdleMode Idle mode setting

3.7.2.20 getInverted()

```
boolean com.revrobotics.CANSparkMax.getInverted ( )
```

Common interface for returning the inversion state of a speed controller.

Returns

isInverted The state of inversion, true is inverted.

3.7.2.21 getMotorTemperature()

```
double com.revrobotics.CANSparkMax.getMotorTemperature ( )
```

Returns

The motor temperature in Celsius.

3.7.2.22 getOpenLoopRampRate()

```
double com.revrobotics.CANSparkMax.getOpenLoopRampRate ( )
```

Get the configured open loop ramp rate

This is the maximum rate at which the motor controller's output is allowed to change.

Returns

ramp rate time in seconds to go from 0 to full throttle.

3.7.2.23 getOutputCurrent()

```
{\tt double\ com.revrobotics.CANSparkMax.getOutputCurrent\ (\ )}
```

Returns

The motor controller's output current in Amps.

3.7.2.24 getPIDController()

```
{\tt CANPIDController\ com.revrobotics.CANSparkMax.getPIDController\ (\ )}
```

Returns

An object for interfacing with the integrated PID controller.

3.7.2.25 getReverseLimitSwitch()

```
\begin{tabular}{ll} $\sf CANDigitalInput com.revrobotics.CANSparkMax.getReverseLimitSwitch ( $\sf CANDigitalInput.LimitSwitchPolarity polarity ) $$
```

Returns

An object for interfacing with the integrated reverse limit switch.

Parameters

polarity Whether the limit switch is normally open or normally closed.

3.7.2.26 getStickyFault()

```
boolean com.revrobotics.CANSparkMax.getStickyFault ( FaultID\ faultID\ )
```

Get the value of a specific sticky fault

Parameters

faultII)	The ID of the sticky fault to retrive
---------	---	---------------------------------------

Returns

True if the sticky fault with the given ID occurred.

3.7.2.27 getStickyFaults()

```
short com.revrobotics.CANSparkMax.getStickyFaults ( )
```

Returns

All sticky fault bits as a short

3.7.2.28 getVoltageCompensationNominalVoltage()

```
\verb|double com.revrobotics.CANSparkMax.getVoltageCompensationNominalVoltage ()|\\
```

Get the configured voltage compensation nominal voltage value

Returns

The nominal voltage for voltage compensation mode.

3.7.2.29 isFollower()

```
\verb|boolean com.revrobotics.CANSparkMax.isFollower ( )|\\
```

Returns whether the controller is following another controller

Returns

True if this device is following another controller false otherwise

3.7.2.30 set()

Common interface for setting the speed of a speed controller.

Parameters

speed The speed to set. Value should be between -1.0 and 1.0.

3.7.2.31 setCANTimeout()

Sets timeout for sending CAN messages.

Parameters

milliseconds	The timeout in milliseconds.
1111111300001143	THE UTICOUT III TIIIIIGCCOTIGG.

Returns

CANError Set to CANError.kOk if successful

3.7.2.32 setClosedLoopRampRate()

Sets the ramp rate for closed loop control modes.

This is the maximum rate at which the motor controller's output is allowed to change.

Parameters

rate	Time in seconds to go from 0 to full throttle.
------	--

Returns

CANError Set to CANError.kOk if successful

3.7.2.33 setIdleMode()

Sets the idle mode setting for the SPARK MAX.

Parameters

```
mode Idle mode (coast or brake).
```

Returns

CANError Set to CANError.kOk if successful

3.7.2.34 setInverted()

Common interface for inverting direction of a speed controller.

Parameters

isInverted	The state of inversion, true is inverted.

3.7.2.35 setOpenLoopRampRate()

```
CANError com.revrobotics.CANSparkMax.setOpenLoopRampRate ( double rate )
```

Sets the ramp rate for open loop control modes.

This is the maximum rate at which the motor controller's output is allowed to change.

Parameters

rate	Time in seconds to go from 0 to full throttle.
------	--

Returns

CANError Set to CANError.kOk if successful

3.7.2.36 setSecondaryCurrentLimit() [1/2]

```
CANError com.revrobotics.CANSparkMax.setSecondaryCurrentLimit ( double limit )
```

Sets the secondary current limit in Amps.

The motor controller will disable the output of the controller briefly if the current limit is exceeded to reduce the current. This limit is a simplified 'on/off' controller. This limit is enabled by default but is set higher than the default Smart Current Limit.

The time the controller is off after the current limit is reached is determined by the parameter limitCycles, which is the number of PWM cycles (20kHz). The recommended value is the default of 0 which is the minimum time and is part of a PWM cycle from when the over current is detected. This allows the controller to regulate the current close to the limit value.

The total time is set by the equation

```
t = (50us - t0) + 50us * limitCycles t = total off time after over current t0 = time from the start of the PWM cycle until over current is detected
```

Parameters

limit	The current limit in Amps.

Returns

CANError Set to CANError.kOk if successful

3.7.2.37 setSecondaryCurrentLimit() [2/2]

Sets the secondary current limit in Amps.

The motor controller will disable the output of the controller briefly if the current limit is exceeded to reduce the current. This limit is a simplified 'on/off' controller. This limit is enabled by default but is set higher than the default Smart Current Limit.

The time the controller is off after the current limit is reached is determined by the parameter limitCycles, which is the number of PWM cycles (20kHz). The recommended value is the default of 0 which is the minimum time and is part of a PWM cycle from when the over current is detected. This allows the controller to regulate the current close to the limit value.

The total time is set by the equation

```
t = (50us - t0) + 50us * limitCycles t = total off time after over current t0 = time from the start of the PWM cycle until over current is detected
```

Parameters

limit	The current limit in Amps.]
chopCycles	The number of additional PWM cycles to turn the driver off after overcurrent is detected.	

Returns

CANError Set to CANError.kOk if successful

```
3.7.2.38 setSmartCurrentLimit() [1/3]
CANError com.revrobotics.CANSparkMax.setSmartCurrentLimit (
```

Sets the current limit in Amps.

int limit)

The motor controller will reduce the controller voltage output to avoid surpassing this limit. This limit is enabled by default and used for brushless only. This limit is highly recommended when using the NEO brushless motor.

The NEO Brushless Motor has a low internal resistance, which can mean large current spikes that could be enough to cause damage to the motor and controller. This current limit provides a smarter strategy to deal with high current draws and keep the motor and controller operating in a safe region.

Parameters

limit The current limit in Amps.

Returns

CANError Set to CANError.kOk if successful

3.7.2.39 setSmartCurrentLimit() [2/3]

Sets the current limit in Amps.

The motor controller will reduce the controller voltage output to avoid surpassing this limit. This limit is enabled by default and used for brushless only. This limit is highly recommended when using the NEO brushless motor.

The NEO Brushless Motor has a low internal resistance, which can mean large current spikes that could be enough to cause damage to the motor and controller. This current limit provides a smarter strategy to deal with high current draws and keep the motor and controller operating in a safe region.

The controller can also limit the current based on the RPM of the motor in a linear fashion to help with controllability in closed loop control. For a response that is linear the entire RPM range leave limit RPM at 0.

Parameters

stallLimit	The current limit in Amps at 0 RPM.
freeLimit	The current limit at free speed (5700RPM for NEO).

Returns

CANError Set to CANError.kOk if successful

3.7.2.40 setSmartCurrentLimit() [3/3]

Sets the current limit in Amps.

The motor controller will reduce the controller voltage output to avoid surpassing this limit. This limit is enabled by default and used for brushless only. This limit is highly recommended when using the NEO brushless motor.

The NEO Brushless Motor has a low internal resistance, which can mean large current spikes that could be enough to cause damage to the motor and controller. This current limit provides a smarter strategy to deal with high current draws and keep the motor and controller operating in a safe region.

The controller can also limit the current based on the RPM of the motor in a linear fashion to help with controllability in closed loop control. For a response that is linear the entire RPM range leave limit RPM at 0.

Parameters

stallLimit	The current limit in Amps at 0 RPM.	
freeLimit	The current limit at free speed (5700RPM for NEO).	
IimitRPM	RPM less than this value will be set to the stallLimit, RPM values greater than limitRPM will scale	
	linearly to freeLimit	

Returns

CANError Set to CANError.kOk if successful

The documentation for this class was generated from the following file:

C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMax.java

3.8 com.revrobotics.CANSparkMaxFrames Class Reference

Classes

- · class BurnFlashOut
- · interface DataFrame
- · class FirmwareIn
- · class FollowerOut
- · class GetParamIn
- · class SetParamOut
- class SetpointOut
- · class Status0In
- class Status1In
- class Status2In
- · class StatusConfigOut

Static Public Member Functions

- static int packFloat32 (double val)
- static double unpackFloat32 (int val)

Static Public Attributes

- static final int CMD API SETPNT SET = 0x001
- static final int CMD_API_DC_SET = 0x002
- static final int CMD_API_SPD_SET = 0x012
- static final int CMD_API_SMART_VEL_SET = 0x013
- static final int CMD_API_POS_SET = 0x032
- static final int CMD_API_VOLT_SET = 0x042
- static final int CMD_API_CURRENT_SET = 0x043
- static final int CMD_API_SMARTMOTION_SET = 0x052
- static final int **CMD_API_STAT0** = 0x060
- static final int CMD_API_STAT1 = 0x061
- static final int CMD API STAT2 = 0x062
- static final int CMD API CLEAR FAULTS = 0x06E
- static final int CMD_API_DRV_STAT = 0x06A
- static final int CMD_API_BURN_FLASH = 0x072
- static final int CMD_API_SET_FOLLOWER = 0x073
- static final int CMD_API_FACTORY_DEFAULT = 0x074
- static final int CMD_API_FACTORY_RESET = 0x075
- static final int CMD API NACK = 0x080
- static final int CMD_API_ACK = 0x081

- static final int CMD API BROADCAST = 0x090
- static final int CMD_API_HEARTBEAT = 0x092
- static final int CMD_API_SYNC = 0x093
- static final int CMD_API_ID_QUERY = 0x094
- static final int CMD API ID ASSIGN = 0x095
- static final int CMD API FIRMWARE = 0x098
- static final int **CMD_API_ENUM** = 0x099
- static final int CMD_API_MECH_POS = 0x0A0
- static final int **CMD_API_I_ACCUM** = 0x0A2
- static final int CMD_API_PARAM_ACCESS = 0x300

The documentation for this class was generated from the following file:

· C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMaxFrames.java

3.9 com.revrobotics.CANSparkMaxLowLevel Class Reference

Inherits SpeedController.

Inherited by com.revrobotics.CANSparkMax.

Classes

- enum ConfigParameter
- · class FollowConfig
- enum MotorType
- enum ParameterStatus
- enum ParameterType
- · enum PeriodicFrame
- class PeriodicStatus0
- class PeriodicStatus1
- class PeriodicStatus2

Public Member Functions

- CANSparkMaxLowLevel (int deviceID, MotorType type)
- int getFirmwareVersion ()
- String getFirmwareString ()
- byte [] getSerialNumber ()
- int getDeviceId ()
- CANError setMotorType (MotorType type)
- MotorType getMotorType ()
- CANError setPeriodicFramePeriod (PeriodicFrame frameID, int periodMs)
- ParameterStatus **setParameter** (ConfigParameter parameterID, double value)
- ParameterStatus setParameter (ConfigParameter parameterID, int value)
- ParameterStatus setParameter (ConfigParameter parameterID, boolean value)
- Optional < Double > getParameterDouble (ConfigParameter parameterID)
- Optional < Integer > getParameterInt (ConfigParameter parameterID)
- Optional < Boolean > getParameterBoolean (ConfigParameter parameterID)
- CANError setEncPosition (double value)
- CANError setlAccum (double value)
- CANError restoreFactoryDefaults ()
- CANError restoreFactoryDefaults (boolean persist)
- ParameterStatus setParameterCore (ConfigParameter parameterID, ParameterType type, int value)
- Optional < Integer > getParameterCore (ConfigParameter parameterID, ParameterType expectedType)
- ParameterType getParameterType (ConfigParameter parameterID)

Static Public Attributes

- static final byte **kNumFirmwareRetries** = 10
- static final int kDefaultCANTimeoutMs = 20
- static final int kDefaultStatus0PeriodMs = 10
- static final int kDefaultStatus1PeriodMs = 20
- static final int kDefaultStatus2PeriodMs = 50
- static final int kMinFirmwareVersion = 0x101001C

Protected Member Functions

- PeriodicStatus0 getPeriodicStatus0 ()
- PeriodicStatus1 getPeriodicStatus1 ()
- PeriodicStatus2 getPeriodicStatus2 ()

Static Protected Member Functions

• static void notifyOnCANDisconnect ()

Protected Attributes

- CAN m_can
- int m_controlPeriodMs
- int m_canTimeoutMs
- boolean m_inverted

3.9.1 Constructor & Destructor Documentation

3.9.1.1 CANSparkMaxLowLevel()

Create a new SPARK MAX Controller

Parameters

deviceID	The device ID.
type	The motor type connected to the controller. Brushless motors must be connected to their matching color and the hall sensor plugged in. Brushed motors must be connected to the Red and Black
	terminals only.

3.9.2 Member Function Documentation

3.9.2.1 getDeviceId() int com.revrobotics.CANSparkMaxLowLevel.getDeviceId () Get the configured Device ID of the SPARK MAX. Returns int device ID

3.9.2.2 getFirmwareString()

```
{\tt String\ com.revrobotics.CANSparkMaxLowLevel.getFirmwareString\ (\ )}
```

Get the firmware version of the SPARK MAX as a string.

Returns

std::string Human readable firmware version string

3.9.2.3 getFirmwareVersion()

```
int com.revrobotics.CANSparkMaxLowLevel.getFirmwareVersion ( )
```

Get the firmware version of the SPARK MAX.

Returns

uint32_t Firmware version integer. Value is represented as 4 bytes, Major.Minor.Build H.Build L

3.9.2.4 getMotorType()

```
MotorType com.revrobotics.CANSparkMaxLowLevel.getMotorType ( )
```

Get the motor type setting for the SPARK MAX.

This uses the Get Parameter API and should be used infrequently. This function uses a non-blocking call and will return a cached value if the parameter is not returned by the timeout. The timeout can be changed by calling SetCANTimeout(int milliseconds)

Returns

MotorType Motor type setting

3.9.2.5 getSerialNumber()

```
\verb|byte[]| com.revrobotics.CANSparkMaxLowLevel.getSerialNumber ()|\\
```

Get the unique serial number of the SPARK MAX. Not currently available.

Returns

byte[] Vector of bytes representig the unique serial number

3.9.2.6 restoreFactoryDefaults() [1/2]

```
CANError com.revrobotics.CANSparkMaxLowLevel.restoreFactoryDefaults ( )
```

Restore motor controller parameters to factory default until the next controller reboot

Returns

CANError Set to CANError::kOk if successful

3.9.2.7 restoreFactoryDefaults() [2/2]

Restore motor controller parameters to factory default

Parameters

persist	If true, burn the flash with the factory default parameters
---------	---

Returns

CANError Set to CANError::kOk if successful

3.9.2.8 setMotorType()

Set the motor type connected to the SPARK MAX.

This uses the Set Parameter API and should be used infrequently. The parameter does not presist unless burn ← Flash() is called. The recommended method to configure this parameter is to use the SPARK MAX GUI to tune and save parameters.

Parameters

type

The type of motor connected to the controller. Brushless motors must be connected to their matching color and the hall sensor plugged in. Brushed motors must be connected to the Red and Black terminals only.

Returns

CANError Set to CANError::kOk if successful

3.9.2.9 setPeriodicFramePeriod()

Set the rate of transmission for periodic frames from the SPARK MAX

Each motor controller sends back three status frames with different data at set rates. Use this function to change the default rates.

Defaults: Status0 - 10ms Status1 - 20ms Status2 - 50ms

This value is not stored in the FLASH after calling burnFlash() and is reset on powerup.

Refer to the SPARK MAX reference manual on details for how and when to configure this parameter.

Parameters

frameID	The frame ID can be one of PeriodicFrame type
periodMs	The rate the controller sends the frame to the controller.

Returns

CANError Set to CANError.kOk if successful

The documentation for this class was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMaxLowLevel.java

3.10 com.revrobotics.CANSparkMaxLowLevel.ConfigParameter Enum Reference

Public Member Functions

ConfigParameter (int value)

Static Public Member Functions

• static ConfigParameter fromId (int id)

Public Attributes

- **kCanID** =(0)
- kInputMode =(1)
- kMotorType =(2)
- kCommAdvance =(3)
- kSensorType =(4)
- kCtrlType =(5)
- kldleMode =(6)
- kInputDeadband =(7)
- kFirmwareVer =(8)
- kHallOffset =(9)
- kPolePairs =(10)
- kCurrentChop =(11)
- kCurrentChopCycles =(12)
- $kP_0 = (13)$
- $kl_0 = (14)$
- **kD_0** =(15)
- kF_0 = (16)
- klZone_0 =(17)
- **kDFilter_0** =(18)
- **kOutputMin_0** =(19)
- **kOutputMax_0** =(20)
- **kP 1** =(21)
- kl_1 =(22)
- kD_1 =(23)
- $kF_1 = (24)$
- kIZone_1 =(25)
- kDFilter_1 =(26)
- **kOutputMin_1** =(27)
- **kOutputMax_1** =(28)
- **kP_2** =(29)
- kl_2 =(30)
- **kD_2** =(31)
- kF 2 =(32)
- klZone_2 =(33)
- kDFilter_2 =(34)
- **kOutputMin_2** =(35)
- **kOutputMax_2** =(36)
- **kP_3** =(37)
- **kl_3** =(38)
- kD 3 =(39)
- $kF_3 = (40)$
- kIZone_3 =(41)
- kDFilter_3 =(42)
- **kOutputMin_3** =(43)
- kOutputMax_3 = (44)
- kReserved =(45)
- kOutputRatio =(46)
- kSerialNumberLow =(47)

- kSerialNumberMid =(48)
- kSerialNumberHigh =(49)
- kLimitSwitchFwdPolarity =(50)
- kLimitSwitchRevPolarity =(51)
- kHardLimitFwdEn =(52)
- kHardLimitRevEn =(53)
- kSoftLimitFwdEn =(54)
- kSoftLimitRevEn =(55)
- kOpenLoopRampRate =(56)
- kFollowerID =(57)
- kFollowerConfig =(58)
- kSmartCurrentStallLimit =(59)
- kSmartCurrentFreeLimit =(60)
- kSmartCurrentConfig =(61)
- kSmartCurrentReserved =(62)
- kMotorKv =(63)
- **kMotorR** =(64)
- kMotorL =(65)
- kMotorRsvd1 =(66)
- kMotorRsvd2 =(67)
- kMotorRsvd3 =(68)
- kEncoderCountsPerRev =(69)
- kEncoderAverageDepth =(70)
- kEncoderSampleDelta =(71)
- kEncoderRsvd0 =(72)
- kEncoderRsvd1 =(73)
- kVoltageCompMode = (74)
- kCompensatedNominalVoltage =(75)
- kSmartMotionMaxVelocity 0 = (76)
- kSmartMotionMaxAccel_0 = (77)
- kSmartMotionMinVelOutput_0 = (78)
- kSmartMotionAllowedClosedLoopError_0 = (79)
- kSmartMotionAccelStrategy_0 =(80)
- kSmartMotionMaxVelocity_1 =(81)
- kSmartMotionMaxAccel_1 =(82)
- kSmartMotionMinVelOutput_1 =(83)
- kSmartMotionAllowedClosedLoopError_1 =(84)
- kSmartMotionAccelStrategy_1 =(85)
- kSmartMotionMaxVelocity_2 =(86)
- kSmartMotionMaxAccel_2 = (87)
- kSmartMotionMinVelOutput 2 = (88)
- kSmartMotionAllowedClosedLoopError_2 =(89)
- kSmartMotionAccelStrategy_2 = (90)
- kSmartMotionMaxVelocity_3 =(91)
- kSmartMotionMaxAccel_3 =(92)
- kSmartMotionMinVelOutput_3 =(93)
- kSmartMotionAllowedClosedLoopError_3 =(94)
- kSmartMotionAccelStrategy_3 = (95)
- kIMaxAccum_0 =(96)
- kSlot3Placeholder1_0 = (97)
- kSlot3Placeholder2 0 = (98)
- kSlot3Placeholder3_0 =(99)
- klMaxAccum_1 =(100)
- kSlot3Placeholder1_1 =(101)
- kSlot3Placeholder2_1 =(102)

- kSlot3Placeholder3_1 =(103)
- kIMaxAccum_2 =(104)
- kSlot3Placeholder1_2 =(105)
- kSlot3Placeholder2_2 =(106)
- kSlot3Placeholder3 2 =(107)
- kIMaxAccum_3 =(108)
- kSlot3Placeholder1_3 =(109)
- kSlot3Placeholder2_3 =(110)
- kSlot3Placeholder3_3 =(111)
- kPositionConversionFactor =(112)
- kVelocityConversionFactor =(113)
- kClosedLoopRampRate =(114)
- · final int value

The documentation for this enum was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMaxLowLevel.java

3.11 com.revrobotics.ControlType Enum Reference

Public Member Functions

• ControlType (int value)

Public Attributes

- kDutyCycle =(0)
- kVelocity =(1)
- kVoltage =(2)
- kPosition =(3)
- kSmartMotion =(4)
- **kCurrent** =(5)
- kSmartVelocity =(6)
- · final int value

The documentation for this enum was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/ControlType.java

3.12 com.revrobotics.CANSparkMaxFrames.DataFrame Interface Reference

Inherited by com.revrobotics.CANSparkMaxFrames.BurnFlashOut, com.revrobotics.CANSparkMaxFrames. \leftarrow FirmwareIn, com.revrobotics.CANSparkMaxFrames.FollowerOut, com.revrobotics.CANSparkMaxFrames.Get \leftarrow ParamIn, com.revrobotics.CANSparkMaxFrames.SetParamOut, com.revrobotics.CANSparkMaxFrames.Setpoint \leftarrow Out, com.revrobotics.CANSparkMaxFrames.Status1In, com. \leftarrow revrobotics.CANSparkMaxFrames.Status2In, and com.revrobotics.CANSparkMaxFrames.StatusConfigOut.

Public Member Functions

- byte [] Serialize ()
- · void Deserialize (byte[] buf)

The documentation for this interface was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMaxFrames.java

3.13 com.revrobotics.CANSparkMax.FaultID Enum Reference

Public Member Functions

• FaultID (int value)

Public Attributes

- kBrownout =(0)
- kOvercurrent =(1)
- kOvervoltage =(2)
- kMotorFault =(3)
- kSensorFault =(4)
- **kStall** =(5)
- **kEEPROMCRC** =(6)
- **kCANTX** =(7)
- kCANRX =(8)
- kHasReset =(9)
- **kDRVFault** =(10)
- kOtherFault =(11)
- kSoftLimitFwd =(12)
- kSoftLimitRev =(13)
- kHardLimitFwd =(14)
- kHardLimitRev =(15)
- · final int value

The documentation for this enum was generated from the following file:

C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMax.java

3.14 com.revrobotics.CANSparkMax.IdleMode Enum Reference

Public Member Functions

• IdleMode (int value)

Static Public Member Functions

• static IdleMode fromId (int id)

Public Attributes

- kCoast =(0)
- kBrake =(1)
- · final int value

The documentation for this enum was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMax.java

3.15 com.revrobotics.CANSparkMax.InputMode Enum Reference

Public Member Functions

• InputMode (int value)

Static Public Member Functions

• static InputMode fromId (int id)

Public Attributes

- **kPWM** =(0)
- kCAN =(1)
- final int value

The documentation for this enum was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMax.java

3.16 com.revrobotics.CANDigitalInput.LimitSwitch Enum Reference

Public Attributes

- kForward
- kReverse

The documentation for this enum was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANDigitaIInput.java

3.17 com.revrobotics.CANDigitalInput.LimitSwitchPolarity Enum Reference

Public Member Functions

• LimitSwitchPolarity (int value)

Public Attributes

- kNormallyOpen =(0)
- kNormallyClosed =(1)
- · final int value

The documentation for this enum was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANDigitaIInput.java

3.18 com.revrobotics.CANSparkMaxLowLevel.MotorType Enum Reference

Public Member Functions

• MotorType (int value)

Public Attributes

- kBrushed =(0)
- kBrushless =(1)
- · final int value

The documentation for this enum was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMaxLowLevel.java

3.19 com.revrobotics.CANSparkMaxLowLevel.ParameterStatus Enum Reference

Public Member Functions

ParameterStatus (int value)

Public Attributes

- **kOK** =(0)
- kInvalidID =(1)
- kMismatchType =(2)
- kAccessMode =(3)
- kInvalid =(4)
- kNotImplementedDeprecated =(5)
- · final int value

The documentation for this enum was generated from the following file:

C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMaxLowLevel.java

3.20 com.revrobotics.CANSparkMaxLowLevel.ParameterType Enum Reference

Public Member Functions

• ParameterType (int value)

Public Attributes

- kInt32 =(0)
- kUint32 =(1)
- kFloat32 =(2)
- **kBool** =(3)
- · final int value

The documentation for this enum was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMaxLowLevel.java

3.21 com.revrobotics.CANSparkMaxLowLevel.PeriodicFrame Enum Reference

Public Member Functions

• PeriodicFrame (int value)

Public Attributes

- **kStatus0** =(0)
- kStatus1 =(1)
- kStatus2 =(2)
- · final int value

The documentation for this enum was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMaxLowLevel.java

3.22 com.revrobotics.CANSparkMaxLowLevel.PeriodicStatus0 Class Reference

Public Attributes

- double appliedOutput
- · short faults
- short stickyFaults
- · byte idleMode
- MotorType motorType
- boolean isFollower

The documentation for this class was generated from the following file:

C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMaxLowLevel.java

3.23 com.revrobotics.CANSparkMaxLowLevel.PeriodicStatus1 Class Reference

Public Attributes

- · double sensorVelocity
- byte motorTemperature
- double busVoltage
- · double outputCurrent

The documentation for this class was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMaxLowLevel.java

3.24 com.revrobotics.CANSparkMaxLowLevel.PeriodicStatus2 Class Reference

Public Attributes

- double sensorPosition
- double iAccum

The documentation for this class was generated from the following file:

C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMaxLowLevel.java

3.25 com.revrobotics.jni.RevJNIWrapper Class Reference

Inherited by com.revrobotics.jni.CANHeartbeatJNI.

The documentation for this class was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/jni/RevJNIWrapper.java

3.26 com.revrobotics.CANSparkMax.SensorType Enum Reference

Public Member Functions

• SensorType (int value)

Static Public Member Functions

• static SensorType fromId (int id)

Public Attributes

- kNoSensor =(0)
- kHallSensor =(1)
- kEncoder =(2)
- final int value

The documentation for this enum was generated from the following file:

• C:/Users/Will/Src/SPARK-MAX-roboRIO/src/main/java/com/revrobotics/CANSparkMax.java

Index

burnFlash	getSmartMotionMinOutputVelocity, 20
com.revrobotics.CANSparkMax, 32	setD, 20, 21
	setDFilter, 21
CANDigitalInput	setFF, 22
com.revrobotics.CANDigitalInput, 6	setl, 23
CANEncoder	setIAccum, 24
com.revrobotics.CANEncoder, 7	setIMaxAccum, 24
CANPIDController	setlZone, 24, 25
com.revrobotics.CANPIDController, 11	setOutputRange, 25, 26
CANSparkMax	setP, 26, 27
com.revrobotics.CANSparkMax, 32	setReference, 27, 28
CANSparkMaxLowLevel	setSmartMotionAccelStrategy, 29
com.revrobotics.CANSparkMaxLowLevel, 48	setSmartMotionAllowedClosedLoopError, 29
clearFaults	setSmartMotionMaxAccel, 29
com.revrobotics.CANSparkMax, 33	setSmartMotionMaxVelocity, 30
close	setSmartMotionMinOutputVelocity, 30
com.revrobotics.CANSparkMax, 33	com.revrobotics.CANPIDController.AccelStrategy, 5
com.revrobotics.CANDigitalInput, 5	com.revrobotics.CANSparkMax, 31
CANDigitalInput, 6	burnFlash, 32
enableLimitSwitch, 6	CANSparkMax, 32
get, 6 isLimitSwitchEnabled, 7	clearFaults, 33
	close, 33
com.revrobotics.CANDigitalInput.LimitSwitch, 56 com.revrobotics.CANDigitalInput.LimitSwitchPolarity, 57	disable, 33
com.revrobotics.CANEncoder, 7	disableVoltageCompensation, 33
CANEncoder, 7	enableVoltageCompensation, 33
getPosition, 8	follow, 34, 35
getPositionConversionFactor, 8	get, 35
get Velocity, 8	getAppliedOutput, 36
getVelocityConversionFactor, 8	getBusVoltage, 36
setPosition, 8	getClosedLoopRampRate, 36
setPositionConversionFactor, 9	getEncoder, 36
setVelocityConversionFactor, 9	getFault, 36
com.revrobotics.CANError, 10	getFaults, 37
com.revrobotics.CANPIDController, 10	getForwardLimitSwitch, 37
CANPIDController, 11	getIdleMode, 37
getD, 12	getInverted, 37
getDFilter, 13	getMotorTemperature, 38
getFF, 13	getOpenLoopRampRate, 38
getl, 14	getOutputCurrent, 38
getlAccum, 14	getPIDController, 38
getlMaxAccum, 15	getReverseLimitSwitch, 39
getlZone, 15	getStickyFault, 40
getOutputMax, 16	getStickyFaults, 40
getOutputMin, 17	getVoltageCompensationNominalVoltage, 40
getP, 18	isFollower, 40
getSmartMotionAccelStrategy, 18	set, 41
getSmartMotionAllowedClosedLoopError, 19	setCANTimeout, 41
getSmartMotionMaxAccel, 19	setClosedLoopRampRate, 41
getSmartMotionMaxVelocity, 20	setIdleMode, 42

62 INDEX

setInverted, 42	getClosedLoopRampRate
setOpenLoopRampRate, 42	com.revrobotics.CANSparkMax, 36
setSecondaryCurrentLimit, 43	getD
setSmartCurrentLimit, 44, 45	com.revrobotics.CANPIDController, 12
com.revrobotics.CANSparkMax.FaultID, 55	getDeviceId
com.revrobotics.CANSparkMax.IdleMode, 55	com.revrobotics.CANSparkMaxLowLevel, 49
com.revrobotics.CANSparkMax.InputMode, 56	getDFilter
com.revrobotics.CANSparkMax.SensorType, 60	com.revrobotics.CANPIDController, 13
com.revrobotics.CANSparkMaxFrames, 46	getEncoder
com.revrobotics.CANSparkMaxFrames.DataFrame, 54	com.revrobotics.CANSparkMax, 36
com.revrobotics.CANSparkMaxLowLevel, 47	getFault
CANSparkMaxLowLevel, 48	com.revrobotics.CANSparkMax, 36
getDeviceId, 49	getFaults
getFirmwareString, 49	com.revrobotics.CANSparkMax, 37
getFirmwareVersion, 49	getFF
getMotorType, 49	com.revrobotics.CANPIDController, 13
getSerialNumber, 49	getFirmwareString
restoreFactoryDefaults, 50	com.revrobotics.CANSparkMaxLowLevel, 49
setMotorType, 50	getFirmwareVersion
setPeriodicFramePeriod, 51	com.revrobotics.CANSparkMaxLowLevel, 49
com.revrobotics.CANSparkMaxLowLevel.ConfigParamete	^r getForwardLimitSwitch
51	com.revrobotics.CANSparkMax, 37
com.revrobotics.CANSparkMaxLowLevel.MotorType, 57	getI
com.revrobotics.CANSparkMaxLowLevel.ParameterStatus	com.revrobotics.CANPIDController, 14
57	getlAccum
com.revrobotics.CANSparkMaxLowLevel.ParameterType,	com.revrobotics.CANPIDController, 14
58	getIdleMode
com.revrobotics.CANSparkMaxLowLevel.PeriodicFrame,	com.revrobotics.CANSparkMax, 37
58	getIMaxAccum
com.revrobotics.CANSparkMaxLowLevel.PeriodicStatus0,	Commercial Control of the Control of
59	getInverted
com.revrobotics.CANSparkMaxLowLevel.PeriodicStatus1,	comine violotics. Or in oparitinax, or
59 com.revrobotics.CANSparkMaxLowLevel.PeriodicStatus2,	getlZone
59	Com.reviobolics.CANFIDController, 15
com.revrobotics.ControlType, 54	getMotorTemperature
com.revrobotics.jni.CANHeartbeatJNI, 10	com.revrobotics.CANSparkMax, 38
com.revrobotics.jni.CANneartbeatoni, 10	getMotorType
confireviobolics.jiii.i tevolvivviappei, 55	com.revrobotics.CANSparkMaxLowLevel, 49
disable	getOpenLoopRampRate
com.revrobotics.CANSparkMax, 33	com.revrobotics.CANSparkMax, 38
disableVoltageCompensation	getOutputCurrent
com.revrobotics.CANSparkMax, 33	com.revrobotics.CANSparkMax, 38
common constant and an analysis	getOutputMax
enableLimitSwitch	com.revrobotics.CANPIDController, 16
com.revrobotics.CANDigitaIInput, 6	getOutputMin
enableVoltageCompensation	com.revrobotics.CANPIDController, 17
com.revrobotics.CANSparkMax, 33	getP
,	com.revrobotics.CANPIDController, 18
follow	getPIDController
com.revrobotics.CANSparkMax, 34, 35	com.revrobotics.CANSparkMax, 38
	getPosition
get	com.revrobotics.CANEncoder, 8
com.revrobotics.CANDigitaIInput, 6	getPositionConversionFactor
com.revrobotics.CANSparkMax, 35	com.revrobotics.CANEncoder, 8
getAppliedOutput	getReverseLimitSwitch
com.revrobotics.CANSparkMax, 36	com.revrobotics.CANSparkMax, 39
getBusVoltage	getSerialNumber
com.revrobotics.CANSparkMax, 36	com.revrobotics.CANSparkMaxLowLevel, 49

INDEX 63

getSmartMotionAccelStrategy	setP
com.revrobotics.CANPIDController, 18	com.revrobotics.CANPIDController, 26, 27
getSmartMotionAllowedClosedLoopError	setPeriodicFramePeriod
com.revrobotics.CANPIDController, 19	com.revrobotics.CANSparkMaxLowLevel, 51
getSmartMotionMaxAccel	setPosition
com.revrobotics.CANPIDController, 19	com.revrobotics.CANEncoder, 8
getSmartMotionMaxVelocity	setPositionConversionFactor
com.revrobotics.CANPIDController, 20	com.revrobotics.CANEncoder, 9
getSmartMotionMinOutputVelocity	setReference
com.revrobotics.CANPIDController, 20	com.revrobotics.CANPIDController, 27, 28
getStickyFault	setSecondaryCurrentLimit
com.revrobotics.CANSparkMax, 40	com.revrobotics.CANSparkMax, 43
getStickyFaults	setSmartCurrentLimit
com.revrobotics.CANSparkMax, 40	com.revrobotics.CANSparkMax, 44, 45
getVelocity	setSmartMotionAccelStrategy
com.revrobotics.CANEncoder, 8	com.revrobotics.CANPIDController, 29
getVelocityConversionFactor	set Smart Motion Allowed Closed Loop Error
com.revrobotics.CANEncoder, 8	com.revrobotics.CANPIDController, 29
getVoltageCompensationNominalVoltage	setSmartMotionMaxAccel
com.revrobotics.CANSparkMax, 40	com.revrobotics.CANPIDController, 29
	setSmartMotionMaxVelocity
isFollower	com.revrobotics.CANPIDController, 30
com.revrobotics.CANSparkMax, 40	setSmartMotionMinOutputVelocity
isLimitSwitchEnabled	com.revrobotics.CANPIDController, 30
com.revrobotics.CANDigitaIInput, 7	setVelocityConversionFactor
rectare Contary Defaults	com.revrobotics.CANEncoder, 9
restoreFactoryDefaults	
com.revrobotics.CANSparkMaxLowLevel, 50	
set	
com.revrobotics.CANSparkMax, 41	
setCANTimeout	
com.revrobotics.CANSparkMax, 41	
setClosedLoopRampRate	
com.revrobotics.CANSparkMax, 41	
setD	
com.revrobotics.CANPIDController, 20, 21	
setDFilter	
com.revrobotics.CANPIDController, 21	
setFF	
com.revrobotics.CANPIDController, 22	
setl	
com.revrobotics.CANPIDController, 23	
setIAccum	
com.revrobotics.CANPIDController, 24	
setIdleMode	
com.revrobotics.CANSparkMax, 42	
setIMaxAccum	
com.revrobotics.CANPIDController, 24	
setInverted	
com.revrobotics.CANSparkMax, 42	
setlZone	
com.revrobotics.CANPIDController, 24, 25	
setMotorType	
com.revrobotics.CANSparkMaxLowLevel, 50	
setOpenLoopRampRate	
com.revrobotics.CANSparkMax, 42	
setOutputRange	
com.revrobotics.CANPIDController, 25, 26	